# Universal Traffic Service

Rate Estimate Web Service Documentation

### Purpose

The purpose of this web service is to allow clients to obtain rate estimates from Universal Traffic Service. They can then use the RateQuoteID returned from estimates in this web service with the Shipment Entry web service.

### Request

The request must be enclosed in a valid SOAP header. An example can be seen below:

#### Request Header Content

HTTP Method: POST URL: <u>http://services.myuts.net/rateestimateservice.asmx</u> SOAP Method: GetRateEstimate WSDL: <u>http://services.myuts.net/rateestimateservice.asmx?WSDL</u>

#### **Request Body Content**

Parameter (length)	Туре	Required	Description
UTS	N/A	Yes	This is the request's root node.
UTS: WebKey	String	Yes	This is a GUID access key provided by UTS which authorizes use of the rate estimate service.
UTS: OriginZip (12)	String	Yes	This is the zip code of the estimate's origin.
UTS: DestinationZip (12)	String	Yes	This is the zip code of the estimate's destination.
UTS: Weight	String	Yes	This is the weight of the line items. This string can be comma delimited to accommodate the weights of multiple line items. Note: The number of comma delimited weight values must be equal to the number of comma delimited class values.

Parameter (length)	Туре	Required	Description
UTS: Class	String	Yes	This is the freight class of the line items. This string can be comma delimited to accommodate the freight classes of multiple line items. Note: The number of comma delimited class values must be equal to the number of comma delimited weight values. Options: 50, 55, 60, 65, 70, 77.5, 85, 92.5, 100, 110, 125, 150, 175, 200, 250, 300, 400, 500
UTS: ShipmentLength	Integer	Yes	This is the total length of the shipment in imperial feet. This defines the number of feet of a trailer the freight will occupy.
UTS: IsStackable	Boolean	Yes	(true/false) If true, line items can be stacked.
UTS: IsHazmat	Boolean	Yes	(true/false) If true, line items are marked as a hazardous material.
UTS: IsTest	Boolean	Yes	(true/false) If true, you will still receive a response but your rate estimate will not be saved for later use.

### Request Body Structure

<UTS>

<WebKey>String</WebKey> <OriginZip> String</OriginZip> <DestinationZip>String</DestinationZip> <Weight>String </Weight> <Class>String</Class> <ShipmentLength>Int</ShipmentLength> <IsStackable>Boolean</IsStackable> <IsHazmat>Boolean</IsHazmat> <IsTest>String</IsTest>

</UTS>

## Response

# Response Body Content

Parameter (length)	Туре	Description
RateEstimate	N/A	This is the response's root node.
RateEstimate: ResponseMessage	String	This will return a success or error message.
RateEstimate: RateQuoteID	String	This is a unique identifier that UTS has applied to the rate estimate. This identifier can be used to assign this rate estimate to a shipment being entered on myUTS or the Shipment Entry web service.
RateEstimate: Origin	N/A	This node contains information about the rate estimate's origin location.

Parameter (length)	Туре	Description
Origin: Name	String	This is the name of the origin location.
Origin: Address	N/A	This node contains information about the rate estimate origin location's address.
Address: Address	String	This is the street address of the origin location.
Address: City	String	This is the city of the origin location.
Address: State	String	This is the state/province of the origin location.
Address: Zip	String	This is the zip/postal code of the origin location.
Address: Country	String	This is the country of the origin location.
RateEstimate: Destination	N/A	This node contains information about the rate estimate's destination location.
Destination: Name	String	This is the name of the origin location.
Destination: Address	N/A	This node contains information about the rate estimate destination location's address.
Address: Address	String	This is the street address of the destination location.
Address: City	String	This is the city of the destination location.
Address: State	String	This is the state/province of the destination location.
Address: Zip	String	This is the zip/postal code of the destination location.
Address: Country	String	This is the country of the destination location.
RateEstimate: CarrierName	String	This is the name of the carrier that was used to calculate the rate of the estimate.
RateEstimate: CarrierID	Integer	This is a UTS-specific, unique identifier for the carrier.
RateEstimate: TransitDays	Integer	This is the estimated number of days necessary to deliver the freight.
RateEstimate: Base	Decimal	This is the cost of the shipment before the fuel surcharge is added.
RateEstimate: FSC	Decimal	This is the estimated cost of the fuel (fuel surcharge).
RateEstimate: Net	Decimal	This is the estimated total cost of the shipment.
RateEstimate: Disclaimer	String	This is a message detailing the terms of our rate estimate system.
Shipment: Warnings	N/A	This node contains all of the individual warnings for the shipment. Each individual warning is represented by a Warning node.
Warnings: Warning	String	This is a single warning message for the shipment. Warning messages contain additional information about the request or the shipment. For instance, in some circumstances UTS cannot return pricing for a shipment. A warning would tell you the reason.

### Response Body Structure

#### <RateEstimate>

- <ResponseMessage>string</ResponseMessage>
- <RateQuoteId>string</RateQuoteId>
- <Origin>
- <Name>String</Name>
- <Address>

<Address>String</Address> <City>String</City> <State> String</State> <Zip>String</Zip> <Country>String</Country> </Address> </Origin> <Destination> <Name>String</Name> <Address> <Address>String</Address> <City>String</City> <State>String</State> <Zip>String</Zip> <Country>String</Country> </Address> </Destination> <CarrierName>String</CarrierName> <CarrierID>Int</CarrierID> <TransitDays>Int</TransitDays> <Base>Decimal</Base> <FSC>Decimal</FSC> <Net>Decimal</Net> <Disclaimer>String</Disclaimer> <Warnings> <Warning>String</Warning> <Warning>String</Warning> </Warnings> </RateEstimate>